

Inspiration Sheet - Diamond Pillar Fun Fold 3 Ways

3 versions of the diamond pillar fun fold card.



Measurements - Version 1

- 4-1/4" x 11" card base
- 1-3/4" x 4" (2) DSP #1
- 1-1/4" x 4" (1) DSP #2
- 1-3/4" x 4" Basic White (1 or 2)
- 1-7/8 x 4-1/8" (2) coordinating cardstock (optional)
- 1-3/8 x 4-1/8" (1) coordinating cardstock (optional)
- 1" x 2" Basic White (pop-out mechanism)
- Focal point shape 3-1/2" or less in diameter.

Directions

1. Score the 4-1/4" x 11" piece at 1-1/2", 3-1/2", 5-1/2", 7-1/2" and 9-1/2".
2. Fold in half at the 5-1/2" score line like a regular card with the opening on the right.
3. Fold the 1-1/2" and 9-1/2" score lines back towards the front and back of the card base. Fold the 3-1/2" and 7-1/2" score lines towards the inside of the card base.
4. Adhere the 1-1/2" sections to each other so the card no longer opens.
5. Score the 1" x 2" piece of Basic White at 1/2" then cut in half so you have two 1" squares scored in half. Adhere half of the folded squares centered on either sides of the score line that separates the two 2" sections. This will be where the focal point is attached. Get as close to the score line with the fold of the squares as possible without overlapping it.
6. Attach the pieces of DSP to the sections created by the score lines, having the 1-3/4" x 4" pieces overlapping the pop-out mechanism.
7. Attach the 1-3/4" x 4" piece(s) of Basic White on the back of the card for personal message.
8. Create a focal point of any shape not exceeding 3-1/2" in diameter and adhere to the other halves of the pop-out mechanism.



Inspiration Sheet - Diamond Pillar Fun Fold 3 Ways

3 versions of the diamond pillar fun fold card.

Measurements - Version 2

- 4-1/4" x 11" card base
- 1-1/4" x 4" (2) DSP #1
- 2-1/4" x 4" (2) Basic White and/or DSP #2
- 1-3/8 x 4-1/8" (2) coordinating cardstock (optional)
- 2-3/8 x 4-1/8" (1) coordinating cardstock (optional)
- 1" x 2" Basic White (pop-out mechanism)
- Focal point shape 2-1/2" x 3-1/2" or less

Directions

1. Score the 4-1/4" x 11" piece at 2-1/2", 4", 5-1/2", 7" and 8-1/2".
2. Fold in half at the 5-1/2" score line like a regular card with the opening on the right (or left).
3. Fold on the other score lines the same way as step 3 for Version 1.
4. Adhere the 2-1/2" sections to each other so the card no longer opens.
5. Create the pop-out mechanism the same way as step 5 for Version 1.
6. Attach the pieces of DSP to the sections created by the score lines (you may also stamp and layer a design on the larger section).
7. Attach the 2-4/4" x 4" piece of Basic White on the back of the card for personal message.
8. Create a focal point of any shape not exceeding 2-1/2" x 3-1/2" and adhere to the other halves of the pop-out mechanism.



Inspiration Sheet - Diamond Pillar Fun Fold 3 Ways

3 versions of the diamond pillar fun fold card.

Measurements - Version 3

- 4-1/4" x 5-1/2" (2) cardbases
- 1-3/4" x 4" (2) DSP #1 and Basic White (2)
- 1/2" x 4" (2) DSP #2
- 1-7/8 x 4-1/8" (2) coordinating cardstock (optional)
- 5/8 x 4-1/8" (1) coordinating cardstock (optional)
- 1" x 2" Basic White (pop-out mechanism)
- Focal point shape 3-1/2" or less in diameter.

Directions

1. Score the 4-1/4" x 5-1/2" pieces at 3/4", 2-3/4" and 4-3/4".
2. Fold in half at the 2-3/4" score line and fold the outside score lines in the opposite direction.
3. Adhere the 3/4" sections to each other.
4. Create the pop-out mechanism the same way as step 5 for Version 1.
5. Attach the pieces of DSP to the sections created by the score lines.
6. Attach the 1-3/4" x 4" pieces of Basic White on the back of the card for personal message.
7. Create a focal point of any shape not exceeding 3-1/2" in diameter and adhere to the other halves of the pop-out mechanism.

